

Package ‘simlandr’

January 23, 2024

Type Package

Title Simulation-Based Landscape Construction for Dynamical Systems

Version 0.3.1

Description A toolbox for constructing potential landscapes for dynamical systems using Monte Carlo simulation. The method is based on the potential landscape definition by Wang et al. (2008) [<doi:10.1073/pnas.0800579105>](https://doi.org/10.1073/pnas.0800579105) (also see Zhou & Li, 2016 [<doi:10.1063/1.4943096>](https://doi.org/10.1063/1.4943096) for further mathematical discussions) and can be used for a large variety of models.

License GPL (>= 3)

URL <https://sciurus365.github.io/simlandr/>,
<https://github.com/Sciurus365/simlandr>

BugReports <https://github.com/Sciurus365/simlandr/issues>

Imports bigmemory, digest, dplyr, forcats, gganimate, ggplot2,
grDevices, htmlwidgets, ks, lifecycle, magrittr, MASS, methods,
plotly, progress, purrr, rlang, tibble

Suggests coda, knitr, rmarkdown, webshot

Encoding UTF-8

RoxygenNote 7.3.0

NeedsCompilation no

Author Jingmeng Cui [aut, cre] ([<https://orcid.org/0000-0003-3421-8457>](https://orcid.org/0000-0003-3421-8457))

Maintainer Jingmeng Cui [<jingmeng.cui@outlook.com>](mailto:jingmeng.cui@outlook.com)

Repository CRAN

Date/Publication 2024-01-23 18:40:09 UTC

R topics documented:

<code>arg_set-class</code>	2
<code>attach_all_matrices</code>	4
<code>autolayer.barrier</code>	4

batch_simulation	5
calculate_barrier	6
check_conv	8
get_dist	9
hash_big_matrix-class	9
make_2d_matrix	10
make_2d_static	11
make_3d_animation	12
make_3d_matrix	14
make_3d_static	15
make_4d_static	16
make_barrier_grid_2d	18
make_barrier_grid_3d	19
plot.landscape	19
save_landscape	20
sim_fun_grad	21
sim_fun_nongrad	22
sim_fun_test	23
summary.barrier	24

Index**25**

arg_set-class	<i>Create and modify argument sets, then make an argument grid for batch simulation</i>
---------------	---

Description

An argument set contains the descriptions of the relevant variables in a batch simulation. Use `new_arg_set()` to create an `arg_set` object, and use `add_arg_ele()` to add an element to the `arg_set`. After adding all elements in the argument set, use `make_arg_grid()` to make an argument grid that can be used directly for running batch simulation.

Usage

```
new_arg_set()

add_arg_ele(arg_set, arg_name, ele_name, start, end, by)

nele(arg_set)

narg(arg_set)

## S3 method for class 'arg_set'
print(x, detail = FALSE, ...)

make_arg_grid(arg_set)
```

```
## S3 method for class 'arg_grid'  
print(x, detail = FALSE, ...)
```

Arguments

arg_set	An arg_set object.
arg_name, ele_name	The name of the argument and its element in the simulation function
start, end, by	The data points where you want to test the variables. Passed to seq.
x	An arg_set object
detail	Do you want to print the object details as a full list?
...	Not in use.

Value

new_arg_set() returns an arg_set object.
add_arg_ele() returns an arg_set object.
nele() returns an integer.
narg() returns an integer.
make_arg_gird() returns an arg_grid object.

Functions

- new_arg_set(): Create an arg_set.
- add_arg_ele(): Add an element to an arg_set.
- nele(): The number of elements in an arg_set.
- narg(): The number of arguments in an arg_set.
- print(arg_set): Print an arg_set object.
- make_arg_grid(): Make an argument grid from an argument set.
- print(arg_grid): Print an arg_grid object

See Also

[batch_simulation\(\)](#) for running batch simulation and a concrete example.

`attach_all_matrices` *Attach all matrices in a batch simulation*

Description

Attach all matrices in a batch simulation

Usage

```
attach_all_matrices(bs, backingpath = "bp")
```

Arguments

`bs` A `batch_simulation` object.
`backingpath` Passed to `bigmemory::as.big.matrix()`.

Value

A `batch_simulation` object with all `hash_big_matrixes` attached.

`autolayer.barrier` *Get a ggplot2 layer from a barrier object*

Description

This layer can show the saddle point (2d) and the minimal energy path (3d) on the landscape.

Usage

```
## S3 method for class 'barrier'
autolayer(object, path = TRUE, ...)
```

Arguments

`object` A barrier object.
`path` Show the minimum energy path in the graph?
`...` Not in use.

Value

A `ggplot2` layer that can be added to an existing landscape plot.

batch_simulation	<i>Perform a batch simulation.</i>
------------------	------------------------------------

Description

Perform a batch simulation.

Usage

```
batch_simulation(arg_grid, sim_fun, default_list, bigmemory = TRUE, ...)
```

```
## S3 method for class 'batch_simulation'
print(x, detail = FALSE, ...)
```

Arguments

arg_grid	An arg_grid object. See make_arg_grid() .
sim_fun	The simulation function. See sim_fun_test() for an example.
default_list	A list of default values for sim_fun.
bigmemory	Use hash_big_matrix-class() to store large matrices?
...	Other parameters passed to sim_fun
x	An arg_set object
detail	Do you want to print the object details as a full list?

Value

A batch_simulation object, also a data frame. The first column, var, is a list of ele_list that contains all the variables; the second to the second last columns are the values of the variables; the last column is the output of the simulation function.

Functions

- `batch_simulation()`: Perform a batch simulation.

Examples

```
batch_arg_set_grad <- new_arg_set()
batch_arg_set_grad <- batch_arg_set_grad %>%
  add_arg_ele(
    arg_name = "parameter", ele_name = "a",
    start = -6, end = -1, by = 1
  )
batch_grid_grad <- make_arg_grid(batch_arg_set_grad)
batch_output_grad <- batch_simulation(batch_grid_grad, sim_fun_grad,
  default_list = list(
    initial = list(x = 0, y = 0),
    parameter = list(a = -4, b = 0, c = 0, sigmasq = 1)
```

```
),  
  length = 1e2,  
  seed = 1614,  
  bigmemory = FALSE  
)  
print(batch_output_grad)
```

calculate_barrier *Functions for calculating energy barrier from landscapes*

Description

Functions for calculating energy barrier from landscapes

Usage

```
calculate_barrier(l, ...)  
  
## S3 method for class ``2d_landscape``  
calculate_barrier(  
  l,  
  start_location_value,  
  start_r,  
  end_location_value,  
  end_r,  
  base = exp(1),  
  ...  
)  
  
## S3 method for class ``3d_landscape``  
calculate_barrier(  
  l,  
  start_location_value,  
  start_r,  
  end_location_value,  
  end_r,  
  Umax,  
  expand = TRUE,  
  omit_unstable = FALSE,  
  base = exp(1),  
  ...  
)  
  
## S3 method for class ``2d_landscape_batch``  
calculate_barrier(  
  l,  
  bg = NULL,
```

```

    start_location_value,
    start_r,
    end_location_value,
    end_r,
    base = exp(1),
    ...
)

## S3 method for class ``3d_landscape_batch``
calculate_barrier(
  l,
  bg = NULL,
  start_location_value,
  start_r,
  end_location_value,
  end_r,
  Umax,
  expand = TRUE,
  omit_unstable = FALSE,
  base = exp(1),
  ...
)

```

Arguments

l	A landscape object.
...	Not in use.
start_location_value, end_location_value	The initial position (in value) for searching the start/end point.
start_r, end_r	The search radius (in L1 distance) for the start/end point.
base	The base of the log function.
Umax	The highest possible value of the potential function.
expand	If the values in the range all equal to Umax, expand the range or not?
omit_unstable	If a state is not stable (the "local minimum" overlaps with the saddle point), omit that state or not?
bg	A 2d_barrier_grid or 3d_barrier_grid object if you want to use different parameters for each condition. Otherwise NULL as default.

Value

A barrier object that contains the (batch) barrier calculation result(s).

 check_conv

Graphical diagnoses to check if the simulation converges

Description

Compare the distribution of different stages of simulation (for `plot_type == "bin"` or `plot_type == "density"`), or show how the percentiles of the distribution evolve over time (for `plot_type == cumuplot`, see [coda::cumuplot\(\)](#) for details). More convergence checking methods for MCMC data are available at the coda package. Be cautious: each convergence checking method has its shortcomings, so do not blindly use any results as the definitive conclusion that a simulation converges or not.

Usage

```
check_conv(output, vars, sample_perc = 0.2, plot_type = "bin")
```

```
## S3 method for class 'check_conv'
print(x, ask = TRUE, ...)
```

Arguments

output	A matrix of simulation output.
vars	The names of variables to check.
sample_perc	The percentage of data sample for the initial, middle, and final stage of the simulation. Not required if <code>plot_type == "cumuplot"</code> .
plot_type	Which type of plots should be generated? ("bin", "density", or "cumuplot" which uses coda::cumuplot())
x	The object.
ask	Ask to press enter to see the next plot?
...	Not in use.

Value

A `check_conv` object that contains the convergence checking result (for `plot_type == "bin"` or `plot_type == "density"`), or draw the cumuplot without a return value (for `plot_type == cumuplot`).

Methods (by generic)

- `print(check_conv)`: Print a `check_conv` object.

get_dist	<i>Get the probability distribution from a landscape object</i>
----------	---

Description

Get the probability distribution from a landscape object

Usage

```
get_dist(l, index = 1)
```

Arguments

l	A landscape project.
index	1 to get the distribution in tidy format; 2 or "raw" to get the raw simulation result (batch_simulation).

Value

A data.frame that contains the distribution in the tidy format or the raw simulation result.

hash_big_matrix-class	<i>Class "hash_big_matrix": big matrix with a md5 hash reference</i>
-----------------------	--

Description

hash_big_matrix class is a modified class from `bigmemory::big.matrix-class()`. Its purpose is to help users operate big matrices within hard disk in a reusable way, so that the large matrices do not consume too much memory, and the matrices can be reused for the next time. Comparing with `bigmemory::big.matrix-class()`, the major enhancement of hash_big_matrix class is that the backing files are, by default, stored in a permanent place, with the md5 of the object as the file name. With this explicit name, hash_big_matrix objects can be easily reloaded into workspace every time.

Usage

```
as_hash_big_matrix(x, backingpath = "bp", silence = TRUE, ...)
```

```
attach_hash_big_matrix(x, backingpath = "bp")
```

Arguments

x	A matrix, vector, or data.frame for <code>bigmemory::as.big.matrix()</code> .
backingpath, ...	Passed to <code>bigmemory::as.big.matrix()</code> .
silence	Suppress messages?

Functions

- `as_hash_big_matrix()`: Create a `hash_big_matrix` object from a matrix.
- `attach_hash_big_matrix()`: Attach a `hash_big_matrix` object from the backing file to the workspace.

Slots

`md5` The md5 value of the matrix.
`address` Inherited from `big.matrix`.

<code>make_2d_matrix</code>	<i>Make a matrix of 2D static landscape plots for one or two parameters</i>
-----------------------------	---

Description

Make a matrix of 2D static landscape plots for one or two parameters

Usage

```
make_2d_matrix(
  bs,
  x,
  rows = NULL,
  cols,
  lims,
  kde_fun = c("ks", "base"),
  n = 200,
  h,
  adjust = 1,
  Umax = 5,
  individual_landscape = TRUE
)
```

Arguments

<code>bs</code>	A <code>batch_simulation</code> object created by <code>[batch_simulation()]</code> .
<code>x</code>	The name of the target variable.
<code>rows, cols</code>	The names of the parameters. <code>rows</code> can be left blank if only one parameter is needed.
<code>lims</code>	The limits of the range for the density estimator as <code>c(xl, xu)</code> for 2D landscapes, <code>c(xl, xu, yl, yu)</code> for 3D landscapes, <code>c(xl, xu, yl, yu, zl, zu)</code> for 4D landscapes. If missing, the range of the data extended by 10% for both sides will be used. For landscapes based on multiple simulations, the largest range of all simulations (which means the lowest lower limit and the highest upper limit) will be used by default.

kde_fun	Which kernel estimator to use? Choices: "ks" <code>ks::kde()</code> (default; faster and using less memory); "base" <code>base::density()</code> (only for 2D landscapes); "MASS" <code>MASS::kde2d()</code> (only for 3D landscapes).
n	The number of equally spaced points in each axis, at which the density is to be estimated.
h	A number, or possibly a vector for 3D and 4D landscapes, specifying the smoothing bandwidth to be used. If missing, the default value of the kernel estimator will be used (but <code>bw = "SJ"</code> for <code>base::density()</code>). Note that the definition of bandwidth might be different for different kernel estimators. For landscapes based on multiple simulations, the largest <code>h</code> of all simulations will be used by default.
adjust	The multiplier to the bandwidth. The bandwidth used is actually <code>adjust * h</code> . This makes it easy to specify values like "half the default" bandwidth.
Umax	The maximum displayed value of potential.
individual_landscape	Make individual landscape for each simulation? Default is TRUE so that it is possible to calculate barriers. Set to FALSE to save time.

Value

A `2d_matrix_landscape` object that describes the landscape of the system, including the smoothed distribution and the landscape plot.

make_2d_static	<i>Make 2D static landscape plot for a single simulation output</i>
----------------	---

Description

Make 2D static landscape plot for a single simulation output

Usage

```
make_2d_static(
  output,
  x,
  lims,
  kde_fun = c("ks", "base"),
  n = 200,
  h,
  adjust = 1,
  Umax = 5
)

make_2d_single(
  output,
  x,
```

```

    lims,
    kde_fun = c("ks", "base"),
    n = 200,
    h,
    adjust = 1,
    Umax = 5
  )

```

Arguments

output	A matrix of simulation output.
x	The name of the target variable.
lims	The limits of the range for the density estimator as <code>c(x1, xu)</code> for 2D landscapes, <code>c(x1, xu, y1, yu)</code> for 3D landscapes, <code>c(x1, xu, y1, yu, z1, zu)</code> for 4D landscapes. If missing, the range of the data extended by 10% for both sides will be used. For landscapes based on multiple simulations, the largest range of all simulations (which means the lowest lower limit and the highest upper limit) will be used by default.
kde_fun	Which kernel estimator to use? Choices: "ks" <code>ks::kde()</code> (default; faster and using less memory); "base" <code>base::density()</code> (only for 2D landscapes); "MASS" <code>MASS::kde2d()</code> (only for 3D landscapes).
n	The number of equally spaced points in each axis, at which the density is to be estimated.
h	A number, or possibly a vector for 3D and 4D landscapes, specifying the smoothing bandwidth to be used. If missing, the default value of the kernel estimator will be used (but <code>bw = "SJ"</code> for <code>base::density()</code>). Note that the definition of bandwidth might be different for different kernel estimators. For landscapes based on multiple simulations, the largest <code>h</code> of all simulations will be used by default.
adjust	The multiplier to the bandwidth. The bandwidth used is actually <code>adjust * h</code> . This makes it easy to specify values like "half the default" bandwidth.
Umax	The maximum displayed value of potential.

Value

A `2d_static_landscape` object that describes the landscape of the system, including the smooth distribution and the landscape plot.

make_3d_animation *Make 3d animations from multiple simulations*

Description

Make 3d animations from multiple simulations

Usage

```

make_3d_animation(
  bs,
  x,
  y,
  fr,
  lims,
  kde_fun = c("ks", "MASS"),
  n = 200,
  h,
  adjust = 1,
  Umax = 5,
  individual_landscape = TRUE,
  mat_3d = FALSE
)

```

Arguments

bs	A batch_simulation object created by [batch_simulation()].
x, y	The names of the target variables.
fr	The names of the parameters used to represent frames in the animation.
lims	The limits of the range for the density estimator as c(x1, xu) for 2D landscapes, c(x1, xu, y1, yu) for 3D landscapes, c(x1, xu, y1, yu, z1, zu) for 4D landscapes. If missing, the range of the data extended by 10% for both sides will be used. For landscapes based on multiple simulations, the largest range of all simulations (which means the lowest lower limit and the highest upper limit) will be used by default.
kde_fun	Which kernel estimator to use? Choices: "ks" ks::kde() (default; faster and using less memory); "base" base::density() (only for 2D landscapes); "MASS" MASS::kde2d() (only for 3D landscapes).
n	The number of equally spaced points in each axis, at which the density is to be estimated.
h	A number, or possibly a vector for 3D and 4D landscapes, specifying the smoothing bandwidth to be used. If missing, the default value of the kernel estimator will be used (but bw = "SJ" for base::density()). Note that the definition of bandwidth might be different for different kernel estimators. For landscapes based on multiple simulations, the largest h of all simulations will be used by default.
adjust	The multiplier to the bandwidth. The bandwidth used is actually adjust * h. This makes it easy to specify values like "half the default" bandwidth.
Umax	The maximum displayed value of potential.
individual_landscape	Make individual landscape for each simulation? Default is TRUE so that it is possible to calculate barriers. Set to FALSE to save time.
mat_3d	Also make the matrix by make_3d_matrix() ? If so, the matrix can be drawn with <code>plot(<landscape>, 3)</code> .

Value

A `3d_animation_landscape` object that describes the landscape of the system, including the smoothed distribution and the landscape plot.

<code>make_3d_matrix</code>	<i>Make a matrix of 3D static landscape plots for one or two parameters</i>
-----------------------------	---

Description

Currently only 3D (x, y, color) is supported. Matrices with 3D (x, y, z) plots are not supported.

Usage

```
make_3d_matrix(
  bs,
  x,
  y,
  rows = NULL,
  cols,
  lims,
  kde_fun = c("ks", "MASS"),
  n = 200,
  h,
  adjust = 1,
  Umax = 5,
  individual_landscape = TRUE
)
```

Arguments

<code>bs</code>	A <code>batch_simulation</code> object created by <code>[batch_simulation()]</code> .
<code>x, y</code>	The names of the target variables.
<code>rows, cols</code>	The names of the parameters. <code>rows</code> can be left blank if only one parameter is needed.
<code>lims</code>	The limits of the range for the density estimator as <code>c(xl, xu)</code> for 2D landscapes, <code>c(xl, xu, yl, yu)</code> for 3D landscapes, <code>c(xl, xu, yl, yu, zl, zu)</code> for 4D landscapes. If missing, the range of the data extended by 10% for both sides will be used. For landscapes based on multiple simulations, the largest range of all simulations (which means the lowest lower limit and the highest upper limit) will be used by default.
<code>kde_fun</code>	Which kernel estimator to use? Choices: "ks" <code>ks:kde()</code> (default; faster and using less memory); "base" <code>base:density()</code> (only for 2D landscapes); "MASS" <code>MASS:kde2d()</code> (only for 3D landscapes).
<code>n</code>	The number of equally spaced points in each axis, at which the density is to be estimated.

h	A number, or possibly a vector for 3D and 4D landscapes, specifying the smoothing bandwidth to be used. If missing, the default value of the kernel estimator will be used (but <code>bw = "SJ"</code> for <code>base::density()</code>). Note that the definition of bandwidth might be different for different kernel estimators. For landscapes based on multiple simulations, the largest h of all simulations will be used by default.
adjust	The multiplier to the bandwidth. The bandwidth used is actually <code>adjust * h</code> . This makes it easy to specify values like "half the default" bandwidth.
Umax	The maximum displayed value of potential.
individual_landscape	Make individual landscape for each simulation? Default is TRUE so that it is possible to calculate barriers. Set to FALSE to save time.

Value

A `3d_matrix_landscape` object that describes the landscape of the system, including the smoothed distribution and the landscape plot.

make_3d_static	<i>Make 3D static landscape plots from simulation output</i>
----------------	--

Description

Make 3D static landscape plots from simulation output

Usage

```
make_3d_static(
  output,
  x,
  y,
  lims,
  kde_fun = c("ks", "MASS"),
  n = 200,
  h,
  adjust = 1,
  Umax = 5
)

make_3d_single(
  output,
  x,
  y,
  lims,
  kde_fun = c("ks", "MASS"),
  n = 200,
```

```

    h,
    adjust = 1,
    Umax = 5
  )

```

Arguments

output	A matrix of simulation output.
x, y	The names of the target variables.
lims	The limits of the range for the density estimator as $c(x_l, x_u)$ for 2D landscapes, $c(x_l, x_u, y_l, y_u)$ for 3D landscapes, $c(x_l, x_u, y_l, y_u, z_l, z_u)$ for 4D landscapes. If missing, the range of the data extended by 10% for both sides will be used. For landscapes based on multiple simulations, the largest range of all simulations (which means the lowest lower limit and the highest upper limit) will be used by default.
kde_fun	Which kernel estimator to use? Choices: "ks" <code>ks::kde()</code> (default; faster and using less memory); "base" <code>base::density()</code> (only for 2D landscapes); "MASS" <code>MASS::kde2d()</code> (only for 3D landscapes).
n	The number of equally spaced points in each axis, at which the density is to be estimated.
h	A number, or possibly a vector for 3D and 4D landscapes, specifying the smoothing bandwidth to be used. If missing, the default value of the kernel estimator will be used (but <code>bw = "SJ"</code> for <code>base::density()</code>). Note that the definition of bandwidth might be different for different kernel estimators. For landscapes based on multiple simulations, the largest <code>h</code> of all simulations will be used by default.
adjust	The multiplier to the bandwidth. The bandwidth used is actually <code>adjust * h</code> . This makes it easy to specify values like "half the default" bandwidth.
Umax	The maximum displayed value of potential.

Value

A `3d_static_landscape` object that describes the landscape of the system, including the smooth distribution and the landscape plot.

make_4d_static

Make 4D static space-color plots from simulation output

Description

Make 4D static space-color plots from simulation output

Usage

```

make_4d_static(
  output,
  x,
  y,
  z,
  lims,
  kde_fun = "ks",
  n = 50,
  h,
  adjust = 1,
  Umax = 5
)

make_4d_single(
  output,
  x,
  y,
  z,
  lims,
  kde_fun = "ks",
  n = 50,
  h,
  adjust = 1,
  Umax = 5
)

```

Arguments

output	A matrix of simulation output.
x, y, z	The names of the target variables.
lims	The limits of the range for the density estimator as $c(x_l, x_u)$ for 2D landscapes, $c(x_l, x_u, y_l, y_u)$ for 3D landscapes, $c(x_l, x_u, y_l, y_u, z_l, z_u)$ for 4D landscapes. If missing, the range of the data extended by 10% for both sides will be used. For landscapes based on multiple simulations, the largest range of all simulations (which means the lowest lower limit and the highest upper limit) will be used by default.
kde_fun	Which kernel estimator to use? Choices: "ks" ks::kde() (default; faster and using less memory); "base" base::density() (only for 2D landscapes); "MASS" MASS::kde2d() (only for 3D landscapes).
n	The number of equally spaced points in each axis, at which the density is to be estimated.
h	A number, or possibly a vector for 3D and 4D landscapes, specifying the smoothing bandwidth to be used. If missing, the default value of the kernel estimator will be used (but <code>bw = "SJ"</code> for <code>base::density()</code>). Note that the definition of bandwidth might be different for different kernel estimators. For landscapes

	based on multiple simulations, the largest h of all simulations will be used by default.
adjust	The multiplier to the bandwidth. The bandwidth used is actually $\text{adjust} * h$. This makes it easy to specify values like "half the default" bandwidth.
Umax	The maximum displayed value of potential.

Value

A `4d_static_landscape` object that describes the landscape of the system, including the smoothed distribution and the landscape plot.

`make_barrier_grid_2d` *Make a grid for calculating barriers for 2d landscapes*

Description

Make a grid for calculating barriers for 2d landscapes

Usage

```
make_barrier_grid_2d(
  ag,
  start_location_value,
  start_r,
  end_location_value,
  end_r,
  df = NULL,
  print_template = FALSE
)
```

Arguments

`ag` An `arg_grid` object.

`start_location_value`, `start_r`, `end_location_value`, `end_r`
Default values for finding local minimum. See [calculate_barrier\(\)](#).

`df` A data frame for the variables. Use `print_template = TRUE` to get a template.

`print_template` Print a template for `df`.

Value

A `barrier_grid_2d` object that specifies the condition for each barrier calculation.

make_barrier_grid_3d *Make a grid for calculating barriers for 3d landscapes*

Description

Make a grid for calculating barriers for 3d landscapes

Usage

```
make_barrier_grid_3d(
  ag,
  start_location_value,
  start_r,
  end_location_value,
  end_r,
  df = NULL,
  print_template = FALSE
)
```

Arguments

ag An arg_grid object.

start_location_value, start_r, end_location_value, end_r
Default values for finding local minimum. See [calculate_barrier\(\)](#).

df A data frame for the variables. Use print_template = TRUE to get a template.

print_template Print a template for df.

Value

A barrier_grid_3d object that specifies the condition for each barrier calculation.

plot.landscape *Make plots from landscape objects*

Description

Make plots from landscape objects

Usage

```
## S3 method for class 'landscape'
plot(x, index = 1, ...)
```

Arguments

x	A landscape object
index	Default is 1. For some landscape objects, there is a second plot (usually 2d heatmaps for 3d landscapes) or a third plot (usually 3d matrices for 3d animations). Use index = 2 to plot that one.
...	Not in use.

Value

The plot.

save_landscape	<i>Save landscape plots</i>
----------------	-----------------------------

Description

Save landscape plots

Usage

```
save_landscape(1, path = NULL, selfcontained = FALSE, ...)
```

Arguments

1	A landscape object
path	The path to save the output. Default: "/pics/x_y.html".
selfcontained	For 'plotly' plots, save the output as a self-contained html file? Default: FALSE.
...	Other parameters passed to htmlwidgets::saveWidget() or ggplot2::ggsave()

Value

The function saves the plot to a specific path. It does not have a return value.

 sim_fun_grad

A simple gradient simulation function for testing

Description

This is a toy stochastic gradient system which can have bistability in some conditions. Model specification:

$$U = x^4 + y^4 + axy + bx + cy$$

$$dx/dt = -\partial U/\partial x + \sigma dW/dt = -4x^3 - ay - b + \sigma dW/dt$$

$$dy/dt = -\partial U/\partial y + \sigma dW/dt = -4y^3 - ax - c + \sigma dW/dt$$

Usage

```
sim_fun_grad(
  initial = list(x = 0, y = 0),
  parameter = list(a = -4, b = 0, c = 0, sigmasq = 1),
  length = 1e+05,
  stepsize = 0.01,
  seed = NULL
)
```

Arguments

initial, parameter	Two sets of parameters. initial contains the initial value of x and y; parameter contains a, b, c, which control the shape of the potential landscape, and sigmasq, which is the square of σ and controls the amplitude of noise.
length	The length of simulation.
stepsize	The step size used in the Euler method.
seed	The initial seed that will be passed to set.seed() function.

Value

A matrix of simulation results.

See Also

[sim_fun_nongrad\(\)](#) and [batch_simulation\(\)](#).

sim_fun_nongrad *A simple non-gradient simulation function for testing*

Description

This is a toy stochastic non-gradient system which can have multistability in some conditions.
Model specification:

Usage

```
sim_fun_nongrad(
  initial = list(x1 = 0, x2 = 0, a = 1),
  parameter = list(b = 1, k = 1, S = 0.5, n = 4, lambda = 0.01, sigmasq1 = 8, sigmasq2 =
    8, sigmasq3 = 2),
  constrain_a = TRUE,
  amin = -0.3,
  amax = 1.8,
  length = 1e+05,
  stepsize = 0.01,
  seed = NULL,
  progress = TRUE
)
```

Arguments

initial, parameter	Two sets of parameters. <code>initial</code> contains the initial value of x_1 , x_2 , and a ; <code>parameter</code> contains b, k, S, n, λ , which control the model dynamics, and $\text{sigmasq1}, \text{sigmasq2}, \text{sigmasq3}$, which are the squares of $\sigma_1, \sigma_2, \sigma_3$ and controls the amplitude of noise.
constrain_a	Should the value of a be constrained? (TRUE by default).
amin, amax	If <code>constrain_a</code> , the minimum and maximum values of a .
length	The length of simulation.
stepsize	The step size used in the Euler method.
seed	The initial seed that will be passed to <code>set.seed()</code> function.
progress	Show progress bar of the simulation?

Details

$$\frac{dx_1}{dt} = \frac{ax_1^n}{S^n + x_1^n} + \frac{bS^n}{S^n + x_2^n} - kx_1 + \sigma_1 dW_1/dt$$

$$\frac{dx_2}{dt} = \frac{ax_2^n}{S^n + x_2^n} + \frac{bS^n}{S^n + x_1^n} - kx_2 + \sigma_2 dW_2/dt$$

$$\frac{da}{dt} = -\lambda a + \sigma_3 dW_3/dt$$

Value

A matrix of simulation results.

References

Wang, J., Zhang, K., Xu, L., & Wang, E. (2011). Quantifying the Waddington landscape and biological paths for development and differentiation. *Proceedings of the National Academy of Sciences*, 108(20), 8257-8262. doi:10.1073/pnas.1017017108

See Also

[sim_fun_grad\(\)](#) and [batch_simulation\(\)](#).

sim_fun_test	<i>A simple simulation function for testing</i>
--------------	---

Description

A simple simulation function for testing

Usage

```
sim_fun_test(par1, par2, length = 1000)
```

Arguments

par1, par2	Two parameters. par1 contains var1; par2 contains var2 and var3.
length	The length of simulation.

Value

A matrix of simulation results.

See Also

[sim_fun_grad\(\)](#) and [sim_fun_nongrad\(\)](#) for more realistic examples.

summary.barrier	<i>Summarize the barrier height from a barrier object</i>
-----------------	---

Description

Summarize the barrier height from a barrier object

Usage

```
## S3 method for class 'barrier'  
summary(object, ...)
```

Arguments

object	A barrier object.
...	Not in use.

Value

A vector (for a single barrier calculation result) or a `data.frame` (for batch barrier calculation results) that contains the barrier heights on the landscape.

Index

`add_arg_ele` (`arg_set`-class), 2
`arg_set`-class, 2
`as_hash_big_matrix`
 (`hash_big_matrix`-class), 9
`attach_all_matrices`, 4
`attach_hash_big_matrix`
 (`hash_big_matrix`-class), 9
`autolayer.barrier`, 4

`batch_simulation`, 5
`batch_simulation()`, 3, 21, 23
`bigmemory::as.big.matrix()`, 4, 9

`calculate_barrier`, 6
`calculate_barrier()`, 18, 19
`check_conv`, 8
`coda::cumplot()`, 8

`get_dist`, 9
`ggplot2::ggsave()`, 20

`hash_big_matrix`
 (`hash_big_matrix`-class), 9
`hash_big_matrix`-class, 9
`htmlwidgets::saveWidget()`, 20

`ks::kde()`, 11–14, 16, 17

`make_2d_matrix`, 10
`make_2d_single` (`make_2d_static`), 11
`make_2d_static`, 11
`make_3d_animation`, 12
`make_3d_matrix`, 14
`make_3d_matrix()`, 13
`make_3d_single` (`make_3d_static`), 15
`make_3d_static`, 15
`make_4d_single` (`make_4d_static`), 16
`make_4d_static`, 16
`make_arg_grid` (`arg_set`-class), 2
`make_arg_grid()`, 5
`make_barrier_grid_2d`, 18

`make_barrier_grid_3d`, 19
`MASS::kde2d()`, 11–14, 16, 17

`narg` (`arg_set`-class), 2
`nele` (`arg_set`-class), 2
`new_arg_set` (`arg_set`-class), 2

`plot.landscape`, 19
`print.arg_grid` (`arg_set`-class), 2
`print.arg_set` (`arg_set`-class), 2
`print.batch_simulation`
 (`batch_simulation`), 5
`print.check_conv` (`check_conv`), 8

`save_landscape`, 20
`sim_fun_grad`, 21
`sim_fun_grad()`, 23
`sim_fun_nongrad`, 22
`sim_fun_nongrad()`, 21, 23
`sim_fun_test`, 23
`sim_fun_test()`, 5
`summary.barrier`, 24